

Hairdressing and Barbering-Infection Prevention and Control Practices How to Clean and Disinfect Scissors and Electric Hair Clipper Blades

• Remove excess hair, clean and disinfect scissors or electric hair clipper blades using a low level disinfectant.

If the scissors or electric hair clipper blades contact non-intact skin, mucous
membranes or penetrate the skin, then clean and disinfect with an intermediate level
disinfectant such as 70% isopropyl alcohol or disinfectant that is Tuberculocidal. The
disinfectant or alcohol must have a drug identification number (DIN) or natural product
number (NPN) from Health Canada.

How to Disinfect Combs and Brushes

- Remove excess hair from combs and brushes. Combs should be cleaned with soap and water and dry before disinfection.
- Immerse combs and brushes in a low-level disinfectant for the appropriate contact time.
- Disinfectant solutions must be made fresh daily or according to the manufacturer's specification.

Using a Straight Blade for Shaving

- If the blade cannot be removed from the handle, then it cannot be used.
- If the blade can be removed, the handle and cradle of the razor, which holds the blade in place, must be cleaned and disinfected with at least a low-level disinfectant after each use. The handle and cradle must be dry before being fully immersed in the disinfectant for 10 minutes.
- Do not leave blades in the holders unless they are to be used immediately on a client.
- Discard disposable blades into an approved sharps container immediately after use.
- Styptic pencils cannot be used to stop clients from bleeding. Styptic powder or liquid is acceptable and must be applied with a disposable applicator.

Re-Use Styling Razors That Come with a Safe Guard

- Styling razors that come with permanent safe guards can be re-used between clients.
- Excess hair needs to be removed between clients and then sprayed with at least a low-level disinfectant.
- When no longer used, discard the styling razor into an approved sharps container. The sharps container cannot be discarded into regular garbage.

How to Clean and Disinfect Crochet Hooks or Tweezers Used for Hair Weaves

- Remove excess hair, clean and disinfect crochet hooks or tweezers using a low level disinfectant.
- If the crochet hooks or tweezers contact non-intact skin, mucous membranes or
 penetrate the skin, then clean and disinfect with an intermediate level disinfectant such
 as 70% isopropyl alcohol or disinfectant that is Tuberculocidal. The disinfectant or
 alcohol must have a drug identification number (DIN) or natural product number (NPN)
 from Health Canada.
- Needles must be discarded into an approved sharps container immediately. The sharps container cannot be discarded into regular garbage.

What to do if Someone is Accidentally Cut

- Before providing any first aid, clean your hands and wear disposable gloves. Then clean your hands again after the gloves are removed.
- Recommend the client seek medical advice.
- Record what happened, including the date and site of injury, the exposed person's name, telephone number, address and the name of the person that provided the service. Keep accidental exposure records for at least three years with a minimum of one year (365 days) on site.
- Go to Spills of <u>Blood and Other Body Fluids</u> if blood or other body fluids are on a surface

Questions/inquiries? Please contact BodySafe at BodySafe@toronto.ca or 416-338-BODY(2639).